

R&D Dept.	Rotem Protocol extract for customers not using WebiSmarts	06/04/2021
DRM-3000/DPU3		Edition: 1.0
DRM-3000 Protocol Explanation and Examples.doc	RD-4-01-1624	Page 1 Out 3

## DRM-3000/DPU3 Protocol Extract

<b>Edited by:</b>	<b>Reviewed by:</b>	<b>Approved by:</b>
Yair Wortzel	Natan Semyonov	Dimitry Ginzburg

R&D Dept.	Rotem Protocol extract	06/04/2021
DRM-3000/DPU3	for customers not using WebiSmarts	Edition: 1.0
DRM-3000 Protocol Explanation and Examples.doc	RD-4-01-1624	Page 2 Out 3

## Scope

This document is an extract from document named "Rotem's New Protocol Structure" (Document reference # RD-4-03-001).

It is aimed to assist users who do not deploy Rotem's WebiSmarts or RMVC software packages to communicate with the DRM-3000/DPU3.

This document provides the essential protocol commands, their description and samples.

### General:

- Each message starts with "\n" character and ends with "\r" character.
- The fourth character corresponds to the detector number (0-4) according to the following:
  - 0 - Internal detector, 1 = External detector 1, 2 - External detector 2, 3 - External detector 3, 4 - AUX (4-20)
  - For example, the message: "\n#1A01\r" sends the message to External Detector number 1.
  - In all the following examples the messages are sent to the Internal detector.
- When there is multiple data to be read, it would be separated by comma ','

### Protocol Messages Examples:

#### 1. Device ID – Read Identification details

- Read message: "\n#10A01\r"
- Response message: "\n#10A09,220,1.15,300019-002,979002,1\r"
  - Detector board FW version number = "1.15"
  - Serial Number = "300019-002"
  - Communication Serial Number (WRM) = "979002"
  - Measuring Units = "1", according to the following:
    - '1' – mR/h, '2' – uSv/h, '3' – uR/h, '4' – CPS, '5' – CPM

#### 2. Current Reading – Reading dose, rate, and status

- Read message: "\n#10B01\r"
- Response message: "\n#10B09,0.02,0.00,1,0.27,0123,\r"
  - Rate = "0.02"
  - Dose = "0.27"
  - Status = "0123"
    - Each char in status value converted to binary value with 4 bits. Each bit indicates if the specific status is on (1) or off (0). List of status bits according to the following:

R&D Dept.	Rotem Protocol extract	06/04/2021
DRM-3000/DPU3	for customers not using WebiSmarts	Edition: 1.0
DRM-3000 Protocol Explanation and Examples.doc	RD-4-01-1624	Page 3 Out 3

Char	Bit3	Bit2	Bit1	Bit0
1	0	0	0	1
Description	N/A	N/A	"Voltage (Battery) Low "	" <b>WRM not mounted</b> "
2	0	0	1	0
Description	"No External Detector detected"	"High Detector Fault"	" <b>Low Detector Fault</b> "	"Low Background"
3	0	0	1	1
Description	"Low H.V"	"High Background"	" <b>Over Threshold</b> "	" <b>Rate Overflow</b> "

- In such a way, the Final Status in the sample above corresponds to: "WRM not mounted, Low Detector Fault, Rate Overflow, Over Threshold"

### 3. Detector's Reset Dose. Message: "\n#10Ah2\r"

### 4. Thresholds – Read and Set detector's thresholds.

- Read Thresholds messages: The bold data is the received threshold.
  - Threshold #1: "\n#10Fa1\r", Response: "\n#10Fa9,**5**\r"
  - Threshold #2: "\n#10Fb1\r", Response: "\n#10Fb9,**67**\r"
  - User Threshold: "\n#10Fc1\r", Response: "\n#10Fa9,**0.5**\r"
- Set Thresholds messages: The bold data is the threshold value to be set.
  - Threshold #1: "\n#10Fa1,**6**\r"
  - Threshold #2: "\n#10Fb1,**10**\r"
  - User Threshold: "\n#10Fc1,**0.8**\r"

### 5. Wireless (WRM) – Turn WRM (wireless) communication on and off.

- Turn WRM on: "\n#10P01,2,**1**,0,Rotem,1234\r".  
This command turns on the transmission using WRM protocol (as described in the user manual) via the WRM wireless module and via the TCP/IP port.
- Turn WRM off: "\n#10P01,2,**0**,0,Rotem,1234\r".  
This message stops the transmission using WRM protocol.